



## Coherency [T3] matrix Elements Processing




**Data Processing: Coherency Elements T3**

Input Directory:

Output Directory:  / **T3** 

Init Row:  End Row:  Init Col:  End Col:

|      |                               |   |   |
|------|-------------------------------|---|---|
| T11  | <input type="radio"/> Modulus | <input checked="" type="radio"/> 10log(Modulus)                             | <input checked="" type="checkbox"/> BMP |
| T12  | <input type="radio"/> Modulus | <input checked="" type="radio"/> 10log(Modulus) <input type="radio"/> Phase | <input checked="" type="checkbox"/> BMP |
| T13  | <input type="radio"/> Modulus | <input checked="" type="radio"/> 10log(Modulus) <input type="radio"/> Phase | <input checked="" type="checkbox"/> BMP |
| T22  | <input type="radio"/> Modulus | <input checked="" type="radio"/> 10log(Modulus)                             | <input checked="" type="checkbox"/> BMP |
| T23  | <input type="radio"/> Modulus | <input checked="" type="radio"/> 10log(Modulus) <input type="radio"/> Phase | <input checked="" type="checkbox"/> BMP |
| T33  | <input type="radio"/> Modulus | <input checked="" type="radio"/> 10log(Modulus)                             | <input checked="" type="checkbox"/> BMP |
| Span | <input type="radio"/> Linear  | <input checked="" type="radio"/> DeciBel = 10log(Span)                      | <input checked="" type="checkbox"/> BMP |

Buttons: **Select All**, **Run**, , **Reset**, **Exit**

### Description:

Creates binary files corresponding to the modulus and argument of the (3x3) complex Coherency matrix ([T3]) raw binary data.  
An option may be set to simultaneously create the corresponding bitmap image files.

### Comments:

Parameters written in Red can be modified directly by the user from the keyboard.

### Input/Output Arguments:

**Input Directory** Indicates the complete location of the considered **MainDirectory / T3 (MD / T3)** containing the [T3] matrix data to be processed.

**Output Directory** Indicates the location of the processed data output directory.  
The default value is set automatically to : **MainDirectory / T3 (MD / T3)**.

## Output Image Number of Rows/Columns:

The output image numbers of rows and columns are initialised to the input data set dimensions.

Users wishing to process a sub-part of the initial image can modify the **Init** and **End** values of the converted images rows and columns.

**Note:** init and end values have to remain within the range defined by the input image dimensions.

## Selection of the Channels to be Processed:

Several channels may be processed at a time. The selection of the BMP options enables the creation of output bmp files.

Users may choose between three types of output binary data :

- **Modulus** : Linear representation of the considered **[T3]** element amplitude. Output file name : Tij\_mod.bin (.bmp)
  - **Modulus** : Element amplitude in dB= $10\log_{10}(\text{Modulus})$ . Output file name : Tij\_dB.bin (.bmp)
  - **Phase** : Argument of the considered complex **[T3]** element (Only available for off-diagonal elements). Output file name : Tij pha.bin (.bmp)
  
  - **Span** : Correspond to the sum of the diagonal elements of **[T3]**, may also be processed (linear and dB) using this program.
-