


H/A/Alpha Decomposition



Data Processing: H / A / Alpha Decomposition

Input Directory: C:/FOULUM_L_Format_PP/C2

Output Directory: C:/FOULUM_L_Format_PP / C2

Init Row: 1 End Row: 1000 Init Col: 1 End Col: 1000

<input checked="" type="checkbox"/> EigenValues (L1, L2)	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> PseudoProbabilities (p1, p2)	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> Alpha1, Alpha2	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> Delta1, Delta2	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> Alpha, Delta, Lambda	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> Lambda	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> Alpha	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> Entropy (H)	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> Anisotropy [A] (p1, p2) <-> Degree of Polarisation	<input checked="" type="checkbox"/> BMP
<input checked="" type="checkbox"/> Combinations (H, A) <input checked="" type="checkbox"/> H A <input checked="" type="checkbox"/> (1 - H) A <input checked="" type="checkbox"/> BMP	
<input checked="" type="checkbox"/> Shannon Entropy (H = Hi + Hp)	<input checked="" type="checkbox"/> BMP

Window Size: 3

Buttons: Run, Reset, Exit

This program creates binary files corresponding to the different polarimetric descriptors obtained from the H/A/Alpha decomposition of the (2x2) complex Covariance matrix [C2] raw binary data.

An option may be set to simultaneously create the corresponding bitmap image files.

Description:

The H/A/Alpha polarimetric decomposition is based on an eigenvector decomposition of the (2*2) complex Covariance [C2] matrix.

The (2x2) complex Covariance [C2] matrix being hermitian, semi-definite positive, its eigenvectors are orthogonal and its eigenvalues are real positive.

The eigenvector decomposition of a distributed target Covariance matrix is considered as a simple statistical model consisting in the expansion of the (2x2) complex Covariance matrix into a weighted sum of two Covariance matrices.

Pseudo-probabilities of the (2x2) complex Covariance [C2] matrix expansion

elements are defined, from the set of sorted eigenvalues.

The distribution of the probabilities can be fully described by two parameters :

- The entropy (**H**) indicates the degree of statistical disorder of the scattering phenomenon.
- For high entropy values, i.e. superior to 0.7, a complementary parameter is necessary to fully characterize the set of probabilities. The anisotropy (**A**) is defined as the relative importance of the secondary scattering mechanisms.

Each unitary eigenvector of the (2x2) complex Covariance [**C2**] matrix may be parameterized using **2** real angular variables.

The condition of mutual orthogonality between the eigenvectors involve that the **2** polarimetric parameters sets resulting from the expansion are not independent. For this reason, each polarimetric parameter is associated to a **2** symbol Bernoulli statistical process.

In this way, the estimate of the mean polarimetric parameter set is given by:

- The Shannon Entropy (**SE**) :

$$SE = SE_I + SE_P$$

Avec :

$$SE_I = 2 \log\left(\frac{\pi Tr[C2]}{2}\right) \quad SE_P = \log\left(4 \frac{det[C2]}{Tr[C2]^2}\right)$$

Shannon entropy of partially polarized and partially coherent light with Gaussian fluctuations, P. Refregier, J. Morio, JOSA A, Vol. 23, Issue 12, pp. 3036-3044, December 2006

Application of Information Theory Measures to Polarimetric and Interferometric SAR Images, J. Morio, P. Refregier, F. Goudail, P. Dubois-Fernandez, X. Dupuis, PSIP 2007, Mulhouse, France

Note : In the Partial Polarimetric Case, the Anisotropy is equivalent and equal to the Wave Degree of Polarization.

Comments:

Parameters written in Red can be modified directly by the user from the keyboard.

Input/Output Arguments:

Input Directory	Indicates the complete location of the considered Main Directory / C2 (MD / C2) containing the [C2] matrix data to be processed.
Output Directory	Indicates the location of the processed data output directory.
	The default value is set automatically to : Main Directory / C2 (MD / C2) .

Output Image Number of Rows/Columns:

The output image numbers of rows and columns are initialised to the input data set dimensions.

Users wishing to process a sub-part of the initial image can modify the **Init** and **End** values of the converted images rows and columns.

Note: init and end values have to remain within the range defined by the input image dimensions.

Processing parameters:

Window Size Data to be decomposed may be processed through an additional filtering procedure consisting of a boxcar filter. Users have then to set the size of the (N*N) sliding window used to compute the local estimate of the average matrix.
The default value of N is set to **0**. Users wishing to avoid additional filtering may set N to **1**.
