



Data Convert (Ixx, Ixy) to (Ixx, Ixy) Multi Look



Description:

This function is used to apply a Multi Look incoherent averaging to real dual polarimetric intensity raw binary data.

Comments:

Blue Parameters may be modified using the widget button : 
 Red Parameters can be modified from keyboard.

Input/Output Arguments:

Input Directory Indicates the location of the considered **Main Directory (MD)** containing the polarimetric data sets to be converted.
Output Directory Indicates the location of the converted data output directory.
 The default value is set automatically to : **Main Directory_MLK**.

Output Image Number of Rows/Columns:

The output image numbers of rows and columns are initialised to the input data set dimensions.
 Users wishing to process a sub-part of the initial image can modify the **Init** and **End** values of the converted images rows and columns.
 Note: init and end values have to remain within the range defined by the input image dimensions.

Processing Parameters:

Multi Look This selection offers the possibility to perform an incoherent multilooking operation during the data conversion.

Partial Polarimetry Data Formats (PPx)

A Partial Polarimetry [**PPx**] representation consists of two polarimetric channels acquired in a reduced polarimetry configuration.

PPx binary data files have to be located in a **PPx directory** located at the same level than a **MD directory** and described by a text configuration file, as follows.
