


Sinclair Elements Processing



Data Processing: Sinclair Elements

Input Directory:

Output Directory:

Init Row: End Row: Init Col: End Col:

S11	<input type="radio"/> A11	<input type="radio"/> I11	<input checked="" type="radio"/> A11 (dB) = I11 (dB)	<input type="radio"/> Phase	<input checked="" type="checkbox"/> BMP
S21	<input type="radio"/> A21	<input type="radio"/> I21	<input checked="" type="radio"/> A21 (dB) = I21 (dB)	<input type="radio"/> Phase	<input checked="" type="checkbox"/> BMP
S12	<input type="radio"/> A12	<input type="radio"/> I12	<input checked="" type="radio"/> A12 (dB) = I12 (dB)	<input type="radio"/> Phase	<input checked="" type="checkbox"/> BMP
S22	<input type="radio"/> A22	<input type="radio"/> I22	<input checked="" type="radio"/> A22 (dB) = I22 (dB)	<input type="radio"/> Phase	<input checked="" type="checkbox"/> BMP
Pauli	<input type="radio"/> Cmplx	<input type="radio"/> Mod	<input checked="" type="radio"/> 20log10(Mod) (dB)	<input type="radio"/> Phase	<input checked="" type="checkbox"/> BMP
Span	<input type="radio"/> Linear	<input checked="" type="radio"/> DeciBel = 10log(Span)			<input checked="" type="checkbox"/> BMP

Buttons: **Select All**, **Reset**, **Run**, **Exit**

Description:

Creates binary files corresponding to the modulus and argument of the (2x2) complex Sinclair [S2] raw binary data.
An option may be set to simultaneously create the corresponding bitmap image files.

Comments:

Parameters written in Red can be modified directly by the user from the keyboard.

Input/Output Arguments:

Input Directory Indicates the complete location of the considered **MainDirectory (MD)** containing the (2x2) complex Sinclair [S2] raw binary data to be processed.

Output Directory Indicates the location of the processed data output directory.
The default value is set automatically to the **MainDirectory (MD)**.

Output Image Number of Rows/Columns:

The output image numbers of rows and columns are initialised to the input data set dimensions.

Users wishing to process a sub-part of the initial image can modify the **Init** and **End** values of the converted images rows and columns.

Note: init and end values have to remain within the range defined by the input image dimensions.

Selection of the Channels to be Processed:

Several channels may be processed at a time. The selection of the BMP options enables the creation of output bmp files.

Users may choose between four types of output binary data :

- **Aij** : Linear representation of the considered complex element amplitude.
Output file name : Aij.bin (.bmp)
 - **Iij** : Linear representation of the considered complex element intensity.
Output file name : Iij.bin (.bmp)
 - **Aij (dB) = Iij (dB)** : Element amplitude in dB = $10\log_{10}(Iij) = 20\log_{10}(Aij)$. Output file name : Iij_dB.bin (.bmp)
 - **Phase** : Argument of the considered complex element. Output file name : Sij pha.bin (.bmp)

 - **Span** : correspond to the sum of the four intensities, may also be processed (linear and dB) using this program.
-