


Correlation Coefficients



Data Processing: Correlation Coefficients (6x6)

Input Master Directory
D:/My_Data_Directory/Master_Dir

Input Slave Directory
D:/My_Data_Directory/Slave_Dir

Output Master-Slave Directory
D:/My_Data_Directory/Master_Dir_Slave_Dir

Init Row: 1 End Row: 900 Init Col: 1 End Col: 1024

Master

☒ Ro12 = (HH1 , HV1) ☒ Ro13 = (HH1 , WV1) ☒ Ro23 = (HV1 , WV1)

Slave

☒ Ro45 = (HH2 , HV2) ☒ Ro46 = (HH2 , WV2) ☒ Ro56 = (HV2 , WV2)

Master - Slave

☒ Ro14 = (HH1 , HH2) ☒ Ro15 = (HH1 , HV2) ☒ Ro16 = (HH1 , WV2)
☒ Ro24 = (HV1 , HH2) ☒ Ro25 = (HV1 , HV2) ☒ Ro26 = (HV1 , WV2)
☒ Ro34 = (WV1 , HH2) ☒ Ro35 = (WV1 , HV2) ☒ Ro36 = (WV1 , WV2)

☒ BMP (Mod / Phase) Window Size : Row ? Col ? **Select All** **Reset**

Run **Exit**

Description:

Creates complex binary files corresponding to the correlation coefficient constructed from the off-diagonal elements of the Pol-InSAR Coherency matrix [T4] or [T6].

An option may be set to simultaneously create the modulus and argument corresponding bitmap image files.

Comments:

Parameters written in Red can be modified directly by the user from the keyboard.

Input/Output Arguments:

- Input Master Directory** Indicates the location of the considered **Master Main Directory (M-MD)** containing the polarimetric data sets to be processed.
- Input Slave Directory** Indicates the location of the considered **Slave Main Directory (S-MD)** containing the polarimetric data sets to be processed.
- Output** Indicates the location of the processed data output directory.

Master-Slave Directory The default value is set automatically to :
Master-MD_Slave-MD (M-MD_S-MD).

Output Image Number of Rows/Columns:

The output image numbers of rows and columns are initialised to the input data set dimensions.

Users wishing to process a sub-part of the initial image can modify the **Init** and **End** values of the converted images rows and columns.

Note: init and end values have to remain within the range defined by the input image dimensions.

Selection of the Channels to be Processed:

Several channels may be processed at a time. The selection of the BMP options enables the creation of output bmp files. Users may choose between two types of bmp outputs :

- **BMP Modulus** : Linear representation of the considered complex correlation coefficient element amplitude. Output file name: RoXX_mod.bmp
- **BMP Phase** : Argument of the considered complex correlation element.
Output file name: RoXX pha.bmp

The output complex binary data file is : RoXX.bin.

Note: Complex format corresponds to 4 bytes interlaced real and imaginary parts.

Processing parameters:

Data to be decomposed may be processed through an additional filtering procedure consisting of a boxcar filter. Users have then to set the size of the (N*N) sliding window used to compute the local estimate of the average matrix.

The default value of N is set to **1** (avoiding any additional filtering).
